
tomahawk Documentation

Release 0.4.4

Kazuhiro Oinuma

March 31, 2012

CONTENTS

WHAT IS TOMAHAWK?

tomahawk enables following 3 things.

- Executes a command into many remote hosts
- Copy files to many remote hosts
- Copy files from remote hosts to local

1.1 Executes a command into many remote hosts

tomahawk is a program that enables to execute a command into many hosts.

```
$ tomahawk -h host1,host2,host3 uptime
```

—> “uptime” command will be executed in host1, host2, and host3 with following output.

```
oinume@host1 % uptime
22:41:27 up 10 days,  3:26,  1 users,  load average: 1.11, 1.13, 1.11

oinume@host2 % uptime
22:41:28 up 20 days,  4:26,  2 users,  load average: 2.11, 2.13, 2.11

oinume@host3 % uptime
22:41:29 up 30 days,  5:26,  3 users,  load average: 3.11, 3.13, 3.11
```

1.2 Copy files to many remote hosts or copy files from remote hosts to local

tomahawk-rsync is a program that enables to copy files <into/from> many hosts.

```
$ tomahawk-rsync -h host1,host2,host3 test.py /tmp/test.py
```

—> “test.py” is copied to host1, host2 and host3.

```
$ tomahawk-rsync -f web.list /usr/local/apache2/conf/httpd.conf /tmp/httpd.conf
```

—> “httpd.conf” is copied to hosts which listed in “web.list”.

```
$ tomahawk-rsync -h host1,host2 -m pull /usr/local/apache2/conf/httpd.conf /tmp/conf/
```

—> “httpd.conf” is copied from host1 and host2 to local directory /tmp/conf as “host1__httpd.conf” and “host2__httpd.conf”.

CONTENTS:

2.1 How to install tomahawk

2.1.1 Requirements

- python \geq 2.4
- argparse
- multiprocessing (required only with python $<$ 2.6)
- pexpect
- nose (required when testing)

2.1.2 Installation

tomahawk distributions is in the [pypi](#), so the easiest way is using pip or easy_install

```
$ sudo pip install tomahawk
```

or

```
$ sudo easy_install tomahawk
```

Or you can use traditional way

```
$ tar xvzf tomahawk-x.y.z.tar.gz  
$ cd tomahawk-x.y.z  
$ sudo python setup.py install
```

2.2 tomahawk manual page

2.2.1 SYNOPSIS

tomahawk [*options*] command

2.2.2 DESCRIPTION

tomahawk is a program that enables to execute a command into many hosts.

```
$ tomahawk -h host1,host2,host3 uptime
```

—> “uptime” command will be executed in host1, host2, and host3 with following output.

```
oinume@host1 % uptime
22:41:27 up 10 days,  3:26,  1 users,  load average: 1.11, 1.13, 1.11

oinume@host2 % uptime
22:41:28 up 20 days,  4:26,  2 users,  load average: 2.11, 2.13, 2.11

oinume@host3 % uptime
22:41:29 up 30 days,  5:26,  3 users,  load average: 3.11, 3.13, 3.11
```

hosts file

-h option enables you to specify hosts, another option ‘-f’, which is specifying hosts files. hosts file is listing host names like this

```
host1
host2
host3
#host4
```

Starting with “#” means commenting the host out.

shell operators

tomahawk executes commands via shell(/bin/sh), so you can use “|” (pipe), &&, || operators and so on.

```
$ tomahawk -h host1,host2 'ps auxww | grep python'
```

2.2.3 OPTIONS

These programs follow the usual GNU command line syntax, with long options starting with two dashes (‘-’). A summary of options is included below. For a complete description, see the Info files.

-h, --hosts

Specifies host names for sending commands. You can specify multiple hosts with ‘,’.

-f, --hosts-files

Specifies hosts files which listed host names for sending commands. You can specify multiple hosts files with ‘,’.

Format of hosts file is below.

```
web01
web02
#web03
web04
```


A line of starting with '#' disables a host.

-l, --prompt-login-password

Prompts a password for ssh authentication at first. If the password is all the same between target hosts, you'll input a password just once.

-s, --prompt-sudo-password

Prompts a password for sudo explicitly. If the password is all the same between target hosts, you'll input a password just once. If commands include "sudo", tomahawk asks sudo password automatically.

-c, --continue-on-error

Continues to send commands even if any errors. The default behavior is fail-safe, means that tomahawk will stop if any errors.

-p, --parallel

Specifies a number of processes for parallel command execution. (default: 1) If your machine has many cpu cores, --parallel 2 .. N might be faster.

-t, --timeout

Specifies timeout seconds for a command.

--expect-timeout

Duplicated. Use t (-timeout) instead.

-u, --ssh-user

Specifies ssh user. The default is a current logged in user.

-o, --ssh-options

Specifies ssh options.

--output-format

Specifies command output format. The default is '`${user}@${host} % ${command}\n${output}\n`'

2.2.4 SEE ALSO

- *tomahawk-rsync* (1)
- *ssh* (1)
- *scp* (1)

2.3 tomahawk-rsync manual page

2.3.1 SYNOPSIS

tomahawk-rsync [*options*] source destination

2.3.2 DESCRIPTION

tomahawk-rsync is a program that enables to copy files <into/from> many hosts.

```
$ tomahawk-rsync -h host1,host2,host3 test.py /tmp/test.py
```

—> “test.py” is copied to host1, host2 and host3.

```
$ tomahawk-rsync -f web.list /usr/local/apache2/conf/httpd.conf /tmp/httpd.conf
```

—> “httpd.conf” is copied to hosts which listed in “web.list”.

```
$ tomahawk-rsync -h host1,host2 -m pull /usr/local/apache2/conf/httpd.conf /tmp/conf/
```

—> “httpd.conf” is copied from host1 and host2 to local directory /tmp/conf as “host1__httpd.conf” and “host2__httpd.conf”.

2.3.3 OPTIONS

These programs follow the usual GNU command line syntax, with long options starting with two dashes (‘-’). A summary of options is included below. For a complete description, see the Info files.

-h, --hosts

Specifies host names for sending commands. You can specify multiple hosts with ‘,’.

-f, --hosts-files

Specifies hosts files which listed host names for sending commands. You can specify multiple hosts files with ‘,’.

Format of hosts file is below.

```
web01
web02
#web03
web04
```

A line of starting with ‘#’ disables a host.

-l, --prompt-login-password

Prompts a password for ssh authentication at first. If the password is all the same between target hosts, you'll input a password just once.

-c, --continue-on-error

Continues to send commands even if any errors. The default behavior is fail-safe, means that tomahawk will stop if any errors.

-p, --parallel

Specifies a number of processes for parallel command execution. (default: 1) If your machine has many cpu cores, `--parallel 2 .. N` might be faster.

-t, --timeout

Specifies timeout seconds for a command.

--output-format

Specifies command output format. The default is `'${user}@${host} % ${command}\n${output}\n'`

-u, --rsync-user

Specifies rsync user. The default is a current logged in user.

-o, --rsync-options

Specifies rsync options. The default is `'-avz'`

-m, --mirror-mode

Selection of "push" or "pull". "pull" means copy files from remote to local (default: "push")

2.3.4 SEE ALSO

- *tomahawk(1)*
- *ssh(1)*
- *rsync(1)*

INDICES AND TABLES

- *search*